Subject: BRenBot to FDS Communication Problem Posted by cmdr1337 on Fri, 13 Feb 2004 02:34:16 GMT

View Forum Message <> Reply to Message

```
#--Start Configuration-IRC-----
# Edit the information below for your setup.
# At least edit BotName and IrcChannel.
BotName = cmdserv
BotFullName = cmdserv
IrcServer = irc.n00bstories.com
IrcPort = 6667
IrcChannel = #cmdserv
#---Q/NickServ------
# Enable auth via "Q" or "Nickserv" below. Sample input is shown.
Qauth = 0
Qusername =
Qpassword =
# Note for Nickserv auth you give the name of nickserv and the full ident string as example
Nickservauth = 1
Nickservname = Nickserv
Nickservauth = identify cmdserv <nick_password>
#--Windows or Linux------
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.
BotMode = WIN32
#--Remote Admin Settings------
# The next 3 lines should be the same info that is in your server.ini
# Note: Although it says "Linux" its the same for Win32 :-)
RenRemLinuxHost = 127.0.0.1
RenRemLinuxPort = 5001
RenRemLinuxPassword = <remote admin password>
#--FDS Installation------
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
FDSConfigFile = C:\Westwood\RenegadeFDS\Server\Data\svrcfg_cnc.ini
FDSLogFilePath = C:\Westwood\RenegadeFDS\Server\
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 600
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 1
# How long people get to place votes. Default here is 60 seconds.
VotingPeriod = 60
# Set vehicle kick to 1 for Sniper servers
VehicleKick = 1
#--BR Configuration Files-----
```

BR Config Files - You shouldn't have to change these names. You can still open them with notepad. AutoAnnounceFile = autoannounce.brf Messagesfile = messages.brf AdminsFile = admins.brf MastersFile = masters.brf KickLogFile = kicklog.brf BanLogfile = banlog.brf #--End Configuration-----

I am running the "snipe only" mod by Vloktboky. since n00bsvr02 uses this (crimson79), I figured it would not be the problem...perhaps I am wrong?