Subject: How do you Change nod and gdi color text?
Posted by DeathC200 on Wed, 25 Feb 2009 23:57:16 GMT

View Forum Message <> Reply to Message

Guys i am wondering how do you change the nod and gdi color text can some one please tell me how i am getting very tired of the red and yellow scheme that i have been using for years:/.

Subject: Re: How do you Change nod and gdi color text? Posted by Gen_Blacky on Thu, 26 Feb 2009 00:14:40 GMT

View Forum Message <> Reply to Message

hud.ini with scripts 3.4.4

read bhs.txt

Subject: Re: How do you Change nod and gdi color text? Posted by DeathC200 on Thu, 26 Feb 2009 01:09:59 GMT

View Forum Message <> Reply to Message

which part of the hud.ini am i gonna need to look for to change the text color of them if you could post a screenshot that would help gratley for the part of changing the text color

Subject: Re: How do you Change nod and gdi color text? Posted by Gen_Blacky on Thu, 26 Feb 2009 01:36:15 GMT

View Forum Message <> Reply to Message

make a hud.ini in your data folder then change these settings

Quote: There is new code that lets you change the color used for the teams (i.e. red for nod and yellow for gdi)

You can also change the public and private message colors.

Note that the hud in ifile is parsed on the server too (for the colored message send commands and the get color engine calls).

This requires bhs.dll on the client.

You create a hud ini file that looks something like this

[General]

NodHouseRed=255

NodHouseGreen=0

NodHouseBlue=0

GDIHouseRed=255

GDIHouseGreen=204

GDIHouseBlue=0

PrivateMessageRed=0

PrivateMessageGreen=0

PrivateMessageBlue=255 PublicMessageRed=255 PublicMessageGreen=255 PublicMessageBlue=255

Subject: Re: How do you Change nod and gdi color text? Posted by Good-One-Driver on Thu, 26 Feb 2009 01:48:41 GMT

View Forum Message <> Reply to Message

Like this?

Register on jelly-server.com then check this thread - http://jelly-server.com/nuke/modules.php?name=FUDForums&file=index&t=msg &th=6367&start=0&S=a2438ee3931fb3c73dbaae1cd833f379

<u>File Attachment</u>s

1) 3.jpg, downloaded 402 times

Page 2 of 5 ---- Generated from

Command and Conquer: Renegade Official Forums



Subject: Re: How do you Change nod and gdi color text? Posted by _SSnipe_ on Thu, 26 Feb 2009 03:29:03 GMT

View Forum Message <> Reply to Message

Gen_Blacky wrote on Wed, 25 February 2009 17:36make a hud.ini in your data folder then change these settings

Quote: There is new code that lets you change the color used for the teams (i.e. red for nod and yellow for gdi)

You can also change the public and private message colors.

Note that the hud.ini file is parsed on the server too (for the colored message send commands and the get color engine calls).

This requires bhs.dll on the client.

You create a hud.ini file that looks something like this

[General]

NodHouseRed=255

NodHouseGreen=0

NodHouseBlue=0

GDIHouseRed=255

GDIHouseGreen=204

GDIHouseBlue=0

PrivateMessageRed=0

PrivateMessageGreen=0

PrivateMessageBlue=255

PublicMessageRed=255

PublicMessageGreen=255

PublicMessageBlue=255

hes right

Subject: Re: How do you Change nod and gdi color text? Posted by DeathC200 on Thu, 26 Feb 2009 03:45:46 GMT

View Forum Message <> Reply to Message

ok but my specific colors are green for nod and orange for gdi

Subject: Re: How do you Change nod and gdi color text? Posted by _SSnipe_ on Thu, 26 Feb 2009 04:05:22 GMT

View Forum Message <> Reply to Message

use paint to get color values if you dont know how ask and ill post picture

Subject: Re: How do you Change nod and gdi color text? Posted by DeathC200 on Thu, 26 Feb 2009 04:38:55 GMT

View Forum Message <> Reply to Message

how do i get the color values i know it may seem stupid but i am learning alot of new stuff this week

Subject: Re: How do you Change nod and gdi color text? Posted by _SSnipe_ on Thu, 26 Feb 2009 04:41:37 GMT

View Forum Message <> Reply to Message

DeathC200 wrote on Wed, 25 February 2009 20:38how do i get the color values i know it may seem stupid but i am learning alot of new stuff this week

http://www.renegadeforums.com/index.php?t=msg&goto=357975&rid=22699&srch=hud.ini#msg_num_10

Subject: Re: How do you Change nod and gdi color text? Posted by DeathC200 on Thu, 26 Feb 2009 04:49:16 GMT

View Forum Message <> Reply to Message

thanks this well help gratfully